

Range Cleaner

Technical Bulletin



Description and Use

Range Cleaner is a heavy duty caustic cleaner for ovens, grills, hotplates and deep fryers.

Features and Benefits

Range Cleaner is a strongly caustic product that quickly removes even heavily baked on soils off ovens, grills and ovens.

Due to its high strength Range Cleaner can also be used diluted with up to 10 parts water for less baked on soils and fatty deposits.

How to Use

Range Cleaner is designed to clean stainless steel, steel and enamelled surfaces. It should not be used on aluminium surfaces such as range hood filters.

Allow equipment to cool below 80°C before using Range Cleaner, then apply to warm surface in neat or diluted form and allow to react for a few minutes. Agitate using a brush, spatula or scourer pad then rinse off with plenty of water. Food contact surfaces such as grill plates can be rinsed with a dilute vinegar solution after water rinsing to ensure all alkaline residues are removed.

To clean deep fryers, empty out the oil and fill with water. Add 1 cup of range Cleaner per 10 litres water and heat to near boiling. Leave to soak, then empty and rinse with water and dry before refilling with oil.

Technical Data

Range Cleaner is based on potassium hydroxide, a strongly caustic ingredient. It also contains a blend of water softening agents and biodegradable detergents for effective cleaning.

Range Cleaner is strongly caustic with a pH of 14 in the neat form.

Pack Sizes

2x5L Bottles:	Code: 11296
15L Drum:	Code: 10924

Accessories

Dispensing bottle labelled "Range Cleaner"	Code: 18777
--	-------------

Dominant Colour Code



Hazard Information

Classified as hazardous according to the criteria of the Globally Harmonised System of Classification and Labelling of Chemicals (GHS).

Eye Damage 1
Skin Corrosion 1A
Metal Corrosion 1
Acute Toxicity 4

DANGER

Causes severe skin burns and eye damage
May be corrosive to metals
Harmful if swallowed

Poisons Schedule: 6
Dangerous Goods: Class 8
UN 1814
PG II

Safety

Range Cleaner is a caustic product. Always wear safety goggles and chemical resistant gauntlet gloves when decanting or using.

If spraying into an oven hold at arm's length and spray slowly using coarse spray to prevent misting.



Range Cleaner

Technical Bulletin

If product causes irritation when spraying, wear a half or full face respirator fitted with P2 or P3 filter.

Range Cleaner must not be sprayed onto hot surfaces >80°C as it can boil off creating highly irritating caustic fumes.

Store in a secure area that can be locked and segregate from any incompatible materials.

Wear protective gloves, eye and body protection. Keep out of reach of children.

